Channel Player Pro



== User Manual==

Channel Player Pro 12 FullHD (CP12)

Recommended System Requirments

Processor : i5 or i7 or Equivalent

RAM: 8 GB or more

Hard Disk Drive : 500 GB or more

Sound Card

Tv Output Graphics Card / Pc To Tv Converter

Windows 10 (64 bit).

Channel Player Pro is a Complete Playout Solutions For TV Channel, Cable TV and IPTV.

Some Option of CP12 —

Program Settings
Program Time Settings
Animated Channel Logo
Animated Special Logo
Animated Timer Logo
Animated Scroll Advertisement
Schedule Video Advertisement
Animated L Shape Ad
Emergency News
Schedule display for upcoming movies
Animated Live Score Board
Live Broadcast
Live IPTV (Optional)

installation -

Step1.

Download Channel Player Pro 12 Full HD, CHANNELHD (Mother Folder of channel player pro) from www.prodipsoft.com then Unzip and install CP12 in your pc.

Step2.

CHANNELHD (Mother Folder of channel player pro) Copy And Paste to "D" Drive.

Step3.

Display Settings:


Set Primary Monitor Resulation is 1366/720 and Secondary Monitor (tv) Resulation 1280/720 Pixel.

Step4.

Run CP12 and Set all Settings Step by Step Then Click Play.

Below Described Some Settings of CP12-


Settings:



A) <u>Film settings by Datewise :</u> Set Films Datewise for 1 Month and Everyday will be Set 7 Films.









B) Film Time Settings



C) Song Settings-

Song will be Autoplay between Film Gape time. Set Songs for 1 Month Together or Set Unique Songs for Everyday.





D) Timer Logo-

Will be Display Timer Logo with Timer.




E) Channel Logo



F) Special Logo



G) Advertisement



a) Scroll Advertisement 1-

For Standerd Crawler Ad, need 4 files.

- 1. Banner: (Format.swf, Width: 1280px, Height: 140px, Frame Rate: 25,)
- 2. Comany Name: (Format.swf, Width: 1280px, Height: 70px, Frame Rate: 25)
- 3. Scroll: (Format .gif/.jpg, Width: 15000px, Height: 70px)
- 4. Side Logo: (Format.swf, Width: 150px, Height: 140px, Frame Rate: 25)
- *software: use swishmax for .swf, Photoshop for gif/jpg

Crwaler Settings:

Click to Scroll Advertisement 1,

Part 1-

Banner : Click to add / Add Banner / select banner File / open / save.

Part 2-


Company Name, Scroll, Side Logo: Click to add / click to Company Name, Scroll, Side Logo tab / Click to Add Company Name Button, Scroll, Side Logo / Click to Company Name, Select Company Name file / Open / Click to Scroll / select scroll file / Open / Click to Side Logo / Select Side Logo / Open / Save.



b) Scroll Advertisement 2-




c) L Shape Ad.



d) **Emergency Scroll News**



e) Schedule Video Advertisement



f) Live Score Board-




H) Azan-



I) Video screen position

If Primary Monitor Resolution is 1366/720 and Secondary Monitor (tv) Resolution 1280/720 Pixel then Video Screen Position Will be 1366.



J) Display Film Name (Title Band)-




K) Set Schedule Screen:




L) Set Break Screen:



M) Set Auto Shutdown Time:



Play



For Any Help /Information Mobile: 0088 01711532492, WhatsApp: 0039 3894592491. email: prodipsoft@gmail.com Web: www.prodipsoft.com